
COSTOS V Enterprise Server Installation Guide

When SQL Server and CostOS Server run on different machines

Before any configuration


 Copy CostOS folder in the C: drive, of the App server. CostOS folder is included in the link that I sent you





C:\C	CostOS\ces\service\wrapper.conf - Notepad++	and the second second	A CONTRACTOR OF THE OWNER		Contraction of the local division of the loc		
	Edit Search View Encoding Language Settings Macro Run Plugins Window ?						
a	≙ 🖹 🖻 🖧 🖧 🖒 🖍 🗖 ⊄ 🖬 🦕 🔍 🖓 🖾 🔚 ୩ 🗐 🖉 🚺 🔍	• D D 🖬 🖪					
	STumi X 📄 wrapper.conf X 📄 jooss-log4jumi X 📄 default.lic X 📄 default.lic X				Function List		
30					-1	<u>A</u>	0
31				- C		Z*	<i>12</i>
	wrapper.java.additional.8=-XX:+UseParallelGC						
33							
34		tem gerver imv MB	eanServerBuilderImn]				
35			camberverbarraerimpi				
	wrapper.java.additional.12=-Dcom.sun.management.jmxremote=true						
37							
38		10					
39							
40	wiapper.Java.addicional.io-2000.sun.management.JMarchage.331-14136						
41	<pre>#wrapper.java.additional.9=-Dgun.rmi.dgc.client.gcInterval=3600000</pre>						
42							
13	<pre>#wrapper.java.additional.10=-Dsession.serialization.jboss=true</pre>						
44	** supper. Jana del final fin del						
45	wrapper.app.parameter.1=org.jboss.Main						
46							
	<pre># Define server name (configuration) - If you need a config that is differe</pre>	nt than the "defa	ult" or need to run multiple confi	.as			
48							
49		listen on a spec	ific IP				
50	wrapper.app.parameter.3=-cdefault						
	# wrapper log location						
52							
53							
54	# You must not change below parameters without first uninstall the service						
55	<pre># service name</pre>			=			
56				1			
57		4. Search for	"wrapper.ntservice.dependency.1=	" and			
58		delete the na	me of sql instance.				
59							
60	# Service dependencies. Add dependencies as needed starting from 1						
61	wrapper.ntservice.dependency.1=						
62							
63	# Mode in which the service is installed. AUTO START or DEMAND START						
64							
	•• vvvvvvvvvv dvvddvvd			+	Function Lis	t	
	l text file len	gth : 3063 lines : 64	Ln:61 Col:32 Sel:16 0	Dos\Windov	vs ANSI as U	TF 0	INS

 Now follow the next steps from the machine that the SQL Server runs

Open SQL Configuration Manager from SQL server and enable the instance such as the following image.









Step 7 – Open SQL Server Management Studio


Connect to Server		X
Servertype:	Database Engine	-
<u>S</u> erver name:	NOMITECH-PC\SQLEXPRESS	•
Authentication:	SQL Server Authentication	•
Login:	sa	•
Password:	*****	
Conne	Remember password Cancel Help Optio	ns >>



Select a page	🔄 Script 👻 📑 Help			
Server Roles User Mapping Securables Status	Login name:	11. Select "S	re "admin" as Login Name GL Server authentication 12. Give "admin" as the	
14. Select "Server Roles"	Enforce password policy Enforce password expira User must change passw Mapped to cettificate Mapped to asymmetric key Map to Credential	ation	13. Untick the check	k boxes
Connection Server: NOMITECH-PC\SQLEXPRESS Connection: Nomitech-PC\Nomitech View connection properties Progress	Mapped Credentials	Credential	Provider	Remove
Ready	Default <u>d</u> atabase: Default lan <u>g</u> uage:	master <default></default>	•	


Give all the roles or just the sysadmin, dbcreator and public.






Select a page	🔄 Script 👻 🔽	Help						
🚰 General 🚰 Options								
	Database <u>n</u> ame	:	CostOS	18. Creat	e a new database			
	<u>O</u> wner:		<default></default>	and nam	e it "CostOS"			
	🔽 Use full-text i	odevina						
	V Decidinent	ndexing						
	Database <u>files</u> :							
	Logical Name	File Type	Filegroup	Initial Size (MB)	Autogrowth			
	CostOS	Rows	PRIMARY	3	By 1 MB, unrestricted growth			
	CostOS_log	Log	Not Applicable	1	By 10 percent, unrestricted growt			
Connection								
Connection Server: NOMITECH-PC\SQLEXPRESS			19.0	lick "OK" to f	inish			
Server: NOMITECH-PC\SQLEXPRESS Connection:			19. C	lick "OK" to f	inish			
Server: NOMITECH-PC\SQLEXPRESS			19. C	lick "OK" to f	inish			
Server: NOMITECH-PC\SQLEXPRESS Connection:			19. C	lick "OK" to f	inish			
Server: NOMITECH-PC\SQLEXPRESS Connection: Nomitech-PC\Nomitech			19. C	lick "OK" to f	inish			
Server: NOMITECH-PC\SQLEXPRESS Connection: Nomitech-PC\Nomitech		III	19. C	lick "OK" to f	inish			
Server: NOMITECH-PC\SQLEXPRESS Connection: Nomitech-PC\Nomitech View connection properties Progress	•	TII.	19. C	lick "OK" to f	finish Remove			
NOMITECH-PC\SQLEXPRESS Connection: Nomitech-PC\Nomitech View connection properties Progress	4	III	19. C		·			


• Follow the next steps from App server.





Step 16 - Follow the same process for default-ds file


<pre>le fet geent jewe incoding inguage stimp: More Nu Nujme Window ?</pre>		OS\ces\server\default\deploy\default-ds.xml - Notepad++	-				X
<pre>introduct @ imagement @ detauted @ detauted @ detauted @ deta</pre>	<u>File E</u> dit	<u>Search View Encoding Language Settings Macro Run Plugins Window</u>	2)
<pre>/ ??ml version="1.0" snooting="UTE-0"?></pre>		🗄 🖻 🗟 🕼 🖧 🔏 🛍 🖿 🗢 🕊 🏙 🦕 🤏 👒 💁 🖬 🌆] 🗷 💽 💽 💌 🔳 🔍 💽				
<pre>/ ??ml version="1.0" snooting="UTE-0"?></pre>	TEST x	mi 🔀 🔚 wrapper conf 🗵 🔚 jboss-log.4j.xml 🕱 🔚 default.lic 🗷 🔚 default lic 🔀	🛯 🔚 costos-ds xml 🔀 🔚 default-ds xml 🛛			Function List	
<pre>closed-uses ULA connection factory config</pre>						Al Al	2
<pre>12 {user-name>admin//sesword></pre>	3 4 5 6 7 E 9 10	<pre></pre>	<pre>p \$> atabaseName=CostOS</pre>	url>			:"1.0"
<pre>13</pre>			class>				
<pre>14 cmetadata> 15 cmetadata> 16 cmetadata> 17 cmetadata> 17 c/local-tx-datasource> 18 c/datasource> 19 cmetoditas 10 cmetadata> 10 cmetadata 10 cmetadatata 10 cmetadatatatatatatatatatat</pre>							
<pre>15</pre>							
<pre>16</pre>							
17 - 18 - 19 -							
18	1000						
19							
	**						
	Viewille	Madain Lanara Cla	Length 506 Error 10		LINITY		TAIC



							Edit	
	Q 🛃 🛛 🖬 🕨 🔳 💵 🛛							
Services (Local)	Services (Local)	-						
	Nomitech CostOS	Name	Description	Status	Startup Type	Log 0 *		
		Alicrosoft Office Groove			Manual	Local		
	Start the service	Microsoft Software Shado	Manages so		Manual	Local		
		🔍 Multimedia Class Schedul	Enables rela	Started	Automatic	Local		
	Description:	🔍 Net.Msmq Listener Adapte	r Receives act		Disabled	Netwo		
	Nomitech CostOS	🔍 Net.Pipe Listener Adapter	Receives act		Disabled	Local		
		🧠 Net.Tcp Listener Adapter	Receives act		Disabled	Local		
		🧠 Net.Tcp Port Sharing Serv	Provides abi		Disabled	Local		
		🔍 Netlogon	Maintains a		Manual	Local		
	your services and search for CostOS", right click on it and	🔍 Network Access Protectio	The Networ		Manual	Netwo		
select "Start		Network Connections		Started	Manual	Local		
select Start	-	Network List Service		Started	Manual	Local		
		Network Location Aware		Started	Automatic	Netwo		
		Network Store Interface S	. This service	Started	Automatic	Local		
		Office Source End St	art	D	Manual Manual	Local Local		
			00	tarted	Automatic	Local		
			ause	tanteu	Manual	Local		
					Manual	Local		
		11	esume		Manual	Local		
		🔛 Peer Networking 0 📃 🔔			Manual	Local		
		Peer Networking Re Re Re	estart					
		Peer Networking I	estart		Manual	Local 🔻		
		Peer Networking I Performance Cour	ll Tasks 🔹 🕨			Local +		
	Extended / Standard /	Peer Networking I Performance Cour				Local +		
Start service Nomitecl	Extended Standard /	Peer Networking I Performance Cour Re	ll Tasks 🔹 🕨			Local +		
Start service Nomitect	<u> </u>	Peer Networking I Performance Cour Re Promance Cour Pr	ll Tasks 🔹 🕨			Local +		

Services (Local)	O. Services (Local)	*				
	SQL Server (SQLEXPRESS)	Name	Description	Status	Startup Type	Log
select to	Stop the service Pause the service Restart the service Description: Provides storage, processing and controlled access of data, and rapid transaction processing. the for the instance that we use, right click on it and "Restart"	 Secondary Logon Secure Socket Tunneling Security Accounts Manager Security Center Sentinel HASP License M Server Shell Hardware Detection Skype Click to Call PNR S Skype Click to Call Updater Skype Updater Smart Card Smart Card Removal Policy SNMP Trap Software Protection SPP Notification Service SQL Active Directory Help 	Enables star Provides su The startup The WSCSV Manages lic Supports fil Provides no Provides ph Downloads Enables the Manages ac Allows the s Receives tra Enables the Provides So Enables inte	Started Started Started Started Started Started	Manual Manual Automatic Automatic (D Automatic Automatic Automatic Automatic Automatic Automatic Manual Manual Manual Manual Disabled	Local Local Local Local Local Local Local Local Local Local Local Netw Local Netw
		SQL Full-text Filter Daem	Service to la	Started Ctarted	Manual Automatic	Local Netw
		SQL Server Agent (: SQL Server Browser St SQL Server Reportir Pa	art op ause esume	arted	Disabled Disabled Automatic	Netw Local Netw
on and Start carvico	SQL Server (SQLEXPRESS) on Local Comp		estart			
pp and start service	SAF Server (SAFEYALKESS) ou Focal Com		ll Tasks	•		
		Re	efresh			
			efresh roperties			

Step 20 - From SQL SERVER MACHINE





 Wait for a couple of minutes and open the administration console going to: <u>http://localhost:8080/ces/</u> please use username/password (admin/admin) to connect for the first time.



• SETTING USERS/ROLES

 Click on User Mgmt in order to see the User Management console. To Create a New CostOS user you must add it from the follow screen:





 Please create one account for every system user. If you specify the CESAdmin role, this user has access to the user management console, and he is a super user for all projects, otherwise he does not.

INSTALLING THE CLIENT APPS


- The client setup files are located in the C: folder of the workstation, you can choose to install between the 32/64 bit applications.
- When the client application starts for the first time it will ask for the server host name/port and a username/password to connect:

Enter your dat	abase password
Host:	costos-server.com:8080
Username:	user
Password:	•••••
Automatica	ally log me in every time the program starts.

- By default CostOS is configured to listen for web service connections on port 8080 so always use the suffix ":8080".
- Please also remember to <u>always</u> store your project files on Shared Network Drives so that they are always accessible from all users.

Step 43 (Configuration 1) – Creating a project db

Open CMD and type commands like the following images.



Command Prompt
C:\CostOS\ces\bin\tools>ProjectDbmsUtil.bat 7. Usage: ProjectDbmsUtil -iudl -i [Install Dbms] <sqlserver!mysql> <unique-dbms-name> <dbms-ip> <dbms-port> <privusername> -u [Update Dbms] <unique-dbms-name> <dbms-ip> <dbms-port> <privusername> -d [Delete Dbms] <unique-dbms-name> -1 [List all Dbms]</unique-dbms-name></privusername></dbms-port></dbms-ip></unique-dbms-name></privusername></dbms-port></dbms-ip></unique-dbms-name></sqlserver!mysql>
C:\CostOS\ces\bin\tools>ProjectDbmsUtil.bat -i SQLServer "CostOS Projects" 192.168.2.5 1433 admin &
CostOS Server Hostname: localhost 9. (App server)
CostOS Server Username: admin 10. (username for Admin user)
CostOS Server Password: 11. (costos password for Admin user)
Successfully Logged-In to CostOS.
Type DBMS password of admin: 12. (password for sql login (admin))
Retype DBMS password of admin: 13. (retype the password for sql login)
DBMS CostOS Projects was successfully added to the installation
C:\CostO\$\ces\bin\tools>

Now each time that you create a new multi – user project, you don't have to add all that information with SQL credents, hostname and ports. You define the Data-source and the Database Server as "**CostOS Projects**".


Project Databas	se Connection Properties	
Data-Source	Database (Multi User)	
Workspace Folder	C:\Users\stavros	Select
Database <mark>Serve</mark> r	CostOS Projects]

Step 46 (Configuration 2) – Stop the Nomitech service first.

Copy the red highlighted line and paste it into the **zdb.properties** file that you will find in C:\CostOS\ces\server\default\deploy\ces.ear\ces.sar.

Command Prompt	Construction of the Article of Spin- of Spin-Street Street
C:\CostOS\ces\bin\tools>setenv.bat1.	
C:\CostOS\ces\bin\tools>set JAVA_HOME=C:\CostOS\jdk	
C:\CostOS\ces\bin\tools>set ANT_OPTS=-Xmx1024M	
osoft SQL Server\Client SDK\ODBC\110\Tools\Binn\;C:\Program Files (x \120\DIS\Binn\;C:\Program Files (x86)\Microsoft SQL Server\120\Tools gram Files\Common Files\Autodesk Shared\;C:\Program Files\Microsoft {	ration\PhysX\Common;C:\Program Files (x86)\Autodesk\Backburner\;C:\Pro 86)\Microsoft SQL Server\120\Tools\Binn\;C:\Program Files\Microsoft SQ \Binn\ManagementStudio\;C:\Program Files (x86)\Microsoft SQL Server\12 SQL Server\Client SDK\ODBC\110\Tools\Binn\;C:\Program Files (x86)\Micr IS\Binn\;C:\Program Files (x86)\Microsoft SQL Server\120\Tools\Binn\Ma stOS\jdk\bin
C:\CostOS\ces\bin\tools>CreateDatasourceConnection.bat 2 Usage: CreateDatasourceConnection dbmstype:hostname:port:dbname:user [dbmstype] database server: sqlserver!mysql [hostname] host of the database server [port] port of the database server [username] username of the database server with update schema right [password] password of the database server C:\CostOS\ces\bin\tools>CreateDatasourceConnection.bat sqlserver:192 Shutdown the server and put the following line to the ces.sar/zdb.pr	SQL SERVER IP Database Name SQL port Login username .168.2.5:1433:CostOS:admin:admin 3.
	00erc1es File. 73-10-39-0521-6B-76-4E-59444C36-2E-69-5E0C-27-4A-147A-3E3E38011614-1A
C:\CostOS\ces\bin\tools> 4. Mark the red highlithed line and	copy it with ENTER

Copy the database credents line and save the file.



• Open Nomitech service again.